

nodectl configure -e (Go into the node control configuration)

1. sudo nodectl configure -e
2. Select No unless support asks

```
=====
=  CONSTELLATION NETWORK HYPERGRAPH  =
=      NODECTL                      =
=  CONFIGURATION TOOL                =
=====
Code Name: Princess Warrior

Welcome to the nodectl configuration tool.


This feature of nodectl will help you initialize a new configuration or update/edit an existing configuration file.

nodectl will attempt to migrate/integrate your configurations changes in order to ensure a smooth transition and operations of your Node via nodectl.

Detailed Mode will walk you through all steps/questions; with detailed explanations of each element of the configuration.
Advanced Mode will be non-verbose, with no walk through explanations, only necessary questions.

The configuration tool does only a limited amount of data type or value verification. After the configuration tool creates a new configuration or edits an existing configuration, it will attempt to verify the end resulting configuration.

You can also choose the -d option at the command line to enter detailed mode directly.
You can also choose the -a option at the command line to enter advanced mode directly.

Switch to advanced mode? [n]: 
```

3. Press enter on this one... just an FYI.

```
=====
=      MAIN MENU                    =
=====

Backup [cn-config.yaml] if exists..... complete
A previous cn-config.yaml was found on the system.

In the event the backup directory was not found, a backup was created in the existing directory. The location is shown below.
/var/tessellation/nodectl/backup_cn-config_2025-06-15-15:52:41Z

Press any key to continue
```

4. Select what item you want to configure. The hot ones are in red...especially Auto Restart

```
----- * NODECTL EDITOR READY * -----
```

```
nodectl configuration yaml was found, loaded, and validated.
```

```
If the configuration found on the node reports a known issue; It is recommended to go through each issue one at a time,  
revalidating the configuration after each edit, in order to make sure that dependent values, are cleared by each edit made.
```

```
If not found, please use the manual setup and consult the Constellation Network Doc Hub for details.
```

```
=====
=                   OPTIONS MENU                   =
=====
```

```
E) Edit Individual Profile Sections
G) Global Pl2 Configuration
I) Internal Cluster Token Identifier
T) Token Cluster Token Coin Id
R) Auto Restart Configuration
L) Set Log Level
P) Passphrase Encryption
D) Setup/Update Delegated Staking
N) Setup Alerting
M) Main Menu
Q) Quit
```

```
KEY PRESS an option
```

Revision #1

Created 15 June 2025 15:50:44 by andy

Updated 15 June 2025 15:57:47 by andy